Motion Mind DC Motor Controller 1.0 Reference Manual

Generated by Doxygen 1.4.6

Tue Apr 11 14:51:00 2006

Contents

| 1 | Motion Mind DC Motor Controller 1.0 Hierarchical Index | 1 |
|---|---|----|
| | 1.1 Motion Mind DC Motor Controller 1.0 Class Hierarchy | 1 |
| 2 | Motion Mind DC Motor Controller 1.0 Class Index | 3 |
| | 2.1 Motion Mind DC Motor Controller 1.0 Class List | 3 |
| 3 | Motion Mind DC Motor Controller 1.0 File Index | 5 |
| | 3.1 Motion Mind DC Motor Controller 1.0 File List | 5 |
| 4 | Motion Mind DC Motor Controller 1.0 Class Documentation | 7 |
| | 4.1 MMClient Class Reference | 7 |
| | 4.2 MMCommand Struct Reference | 11 |
| | 4.3 MMData Struct Reference | 12 |
| | 4.4 MMServer Class Reference | 14 |
| | 4.5 MotionMind Class Reference | 16 |
| 5 | Motion Mind DC Motor Controller 1.0 File Documentation | 23 |
| | 5.1 MMClientServer.hpp File Reference | 23 |
| | 5.2 MotionMind.hpp File Reference | 25 |

Motion Mind DC Motor Controller 1.0 Hierarchical Index

1.1 Motion Mind DC Motor Controller 1.0 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

| MMClient | 7 |
|------------|----|
| MMCommand | 11 |
| MMData | 12 |
| MMServer | 14 |
| MotionMind | 16 |

| 2 | Motion I | Mind DC | Motor | Controller | 1.0 Hierar | chical Index |
|---|----------|---------|-------|------------|------------|--------------|
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |
| | | | | | | |

Motion Mind DC Motor Controller 1.0 Class Index

2.1 Motion Mind DC Motor Controller 1.0 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

| MMClient (A non-blocking client to MMServer) | 7 |
|--|----|
| MMCommand | 11 |
| MMData | 12 |
| MMServer (Provides a server for motion mind controller) | 14 |
| MotionMind (A driver for the Solutions Cubed Motion Mind DC motor controller Revi- | |
| $\operatorname{sion} 4$) | 16 |

| 4 | Motion Mind DC Motor Controller 1.0 Class Index |
|---|---|
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |

Motion Mind DC Motor Controller 1.0 File Index

| 2 1 | Motion | Mind D | C Motor | Controller | 1 N | File | Liet |
|------|--------|--------|---------|------------|-----|------|------|
| ა. I | MOUOM | | | Commoner | 1.0 | тпе | பாதர |

Here is a list of all files with brief descriptions:

| MMClientServer.hpp | | | | | | | | | | | | | | | | | | | 2 | 3 |
|--------------------|--|--|--|--|--|--|--|--|--|--|--|--|--|--|--|--|--|--|---|---|
| MotionMind.hpp | | | | | | | | | | | | | | | | | | | 2 | 5 |

| 6 | Motion Mind | DC Motor | $\mathbf{Controller}$ | 1.0 File Index |
|---|-------------|----------|-----------------------|----------------|
| | | | | |
| | | | | |
| | | | | |
| | | | | |
| | | | | |
| | | | | |
| | | | | |
| | | | | |

Motion Mind DC Motor Controller 1.0 Class Documentation

4.1 MMClient Class Reference

```
A non-blocking client to MMServer.
#include <MMClientServer.hpp>
```

Public Member Functions

- MMClient (char *shmName="mmc0")
- ~MMClient ()
- int isServerStatusOk ()
- void changeSpeed (int16 t speed)
- void moveToAbsolute (int32 t position)
- void moveToRelative (int32 t position)
- void moveAtVelocity (int16 t velocity)
- int32 t getPosition ()

4.1.1 Detailed Description

A non-blocking client to MMServer.

Use an object of this class to command the Motion Mind Controller through a server. The functionality is restricted to setting speed and position using modes 3 or 4 of the controller (serial open loop, and serial closed loop PID, respectively)

Example Program:

```
#include <stdio.h>
#include "MMClientServer.hpp"
#include <pthread.h>
#include <unistd.h>
#include <math.h>
//------
int client()
{
int t = 0;
MMClient mmClient("/mmc0");
if(mmClient.isServerStatusOk() != 0) {
 fprintf(stderr, "[client]: ERROR in server.\n");
 return -1;
while(1) {
 if(mmClient.isServerStatusOk() != 0) {
  fprintf(stderr, "[client]: ERROR in server.\n");
 return -1:
 mmClient.moveAtVelocity((int)(sin((float)t) * 100.0));
 fprintf(stdout, "%d\n", mmClient.getPosition());
 t+=1;
 sleep(1);
}
return 0;
//-----
void *server(void *arg)
MMServer mmServer("/mmc0", "/dev/ser1", 19200, 1);
if(mmServer.getStatusCode() != 0) {
 fprintf(stderr, "[server]: %s\n", mmServer.getStatusMessage());
 return (void *)(-1);
mmServer.doMainLoop(10);
return 0;
//------
// main function
//------
int main()
pthread_t threadId;
pthread_create(&threadId, NULL, &server, NULL);
sleep(1);
client();
return 0;
```

4.1.2 Constructor & Destructor Documentation

4.1.2.1 MMClient::MMClient (char * shmName = "mmc0")

The default constructor. Initiates connection with server

Parameters:

shmName The server (MMServer class) identifier

4.1.2.2 MMClient::~MMClient ()

The default destructor. Disconnects from server.

4.1.3 Member Function Documentation

4.1.3.1 void MMClient::changeSpeed (int16 t speed)

Modifies speed and direction of motor when controller is operated in mode 3 (serial open loop control).

Parameters:

speed Value in the range -1023 to +1023. The direction is determined by the sign (- reverse, + forward) and the the absolute value sets the duty cycle of the input voltage (for example -512 => motor is driven in reverse with 50% duty cycle). The timer register (MMReg_timer) and the velocity limit register (MMReg_velocityLimit) determines the ramp up time required to achieve the new speed.

4.1.3.2 int32 t MMClient::getPosition ()

The client continuously receives an update for actual motor position. This position data is updated only as fast as the server can provide this information, and hence, not guaranteed to be exactly correct. Use this method to get a rough estimate for motor position.

4.1.3.3 int MMClient::isServerStatusOk ()

Returns:

0 if server status is OK, else -1.

4.1.3.4 void MMClient::moveAtVelocity (int16 t velocity)

Specify velocity when operating in mode 4 (serial closed loop). The PID filter must be tuned to get best results.

Parameters:

velocity The desired velocity as a 2's compliment integer. The velocity measurement in the controller occurs over a 5 ms period. Hence, the desired velocity setting can be computed from the following equation: velocity = (MotorShaftRotations/Second * EncoderCount-PerRotation * GearRatio)/50. Use negative values for motion in reverse direction.

4.1.3.5 void MMClient::moveToAbsolute (int32 t position)

Specify an absolute motor position when operating in mode 4 (serial closed-loop). Ensure that the PID filter is tuned, and note that the encoder is decoded on a 4:1 ratio (i.e., if the encoder gives 500 pulses for 1 rotation of the shaft, send 2000 to rotate motor shaft by one full rotation.

Parameters:

position Absolute position as a 32 bit 2's compliment number. Set velocity limit bit in the function register (MMFunc_velocityLimit) and load velocity limit register (mmcreg_-velocityLimit) to limit average velocity during motion.

4.1.3.6 void MMClient::moveToRelative (int32 t position)

Specify movement to a position relative to current position, when operating in mode 4 (serial closed loop). Ensure that the PID filter is tuned, and note that the encoder is decoded on a 4:1 ratio (i.e., if the encoder gives 500 pulses for 1 rotation of the shaft, send 2000 to rotate motor shaft by one full rotation.

Parameters:

position Relative position as a 32 bit 2's compliment number. Set velocity limit bit in the function register (MMFunc_velocityLimit) and load velocity limit register (MMReg_-velocityLimit) to limit average velocity during motion.

The documentation for this class was generated from the following file:

• MMClientServer.hpp

4.2 MMCommand Struct Reference

#include <MMClientServer.hpp>

Public Attributes

- sem t guard
- char command
- \bullet int32_t data
- \bullet int32_t position
- char status

4.2.1 Member Data Documentation

- 4.2.1.1 char MMCommand::command
- 4.2.1.2 int32 t MMCommand::data
- 4.2.1.3 sem t MMCommand::guard
- 4.2.1.4 int32 t MMCommand::position
- 4.2.1.5 char MMCommand::status

The documentation for this struct was generated from the following file:

 $\bullet \ \ MMClientServer.hpp$

4.3 MMData Struct Reference

#include <MotionMind.hpp>

Public Attributes

- int32_t position
- int16_t velocityLimit
- \bullet int8_t velocityFf
- int16 t function
- int16 t pTerm
- \bullet int16_t iTerm
- int16_t dTerm
- \bullet int8_t address
- \bullet int8_t pidScalar
- \bullet int8_t timer
- $\bullet \ \, int16_t \,\, rcMax$
- $int16_t rcMin$
- int16 t rcBand
- int16 t rcCount
- \bullet int16_t velocity
- \bullet int32_t time
- \bullet int16_t status
- \bullet int8_t revision
- int8_t mode
- \bullet int16_t analogCon
- \bullet int16_t analogFbck
- int16 t pwmOut
- \bullet int32_t indexPos

4.3.1 Member Data Documentation

```
{\bf 4.3.1.1 \quad int8\_t \ MMData:: address}
```

- 4.3.1.2 int16 t MMData::analogCon
- 4.3.1.3 int16 t MMData::analogFbck
- 4.3.1.4 int16 t MMData::dTerm
- 4.3.1.5 int16 t MMData::function
- 4.3.1.6 int32 t MMData::indexPos
- 4.3.1.7 int16 t MMData::iTerm
- 4.3.1.8 int8 t MMData::mode
- 4.3.1.9 int8 t MMData::pidScalar
- 4.3.1.10 int32_t MMData::position
- 4.3.1.11 int16 t MMData::pTerm
- 4.3.1.12 int16 t MMData::pwmOut
- 4.3.1.13 int16 t MMData::rcBand
- 4.3.1.14 int16 t MMData::rcCount
- 4.3.1.15 int16 t MMData::rcMax
- 4.3.1.16 int16 t MMData::rcMin
- 4.3.1.17 int8 t MMData::revision
- 4.3.1.18 int16 t MMData::status
- 4.3.1.19 int32 t MMData::time
- 4.3.1.20 int8 t MMData::timer
- 4.3.1.21 int16 t MMData::velocity
- 4.3.1.22 int8 t MMData::velocityFf
- 4.3.1.23 int16 t MMData::velocityLimit

The documentation for this struct was generated from the following file:

• MotionMind.hpp

4.4 MMServer Class Reference

Provides a server for motion mind controller.

#include <MMClientServer.hpp>

Public Member Functions

- MMServer (const char *serverName, const char *port, int baud, int address, bool verbose=true)
- ~MMServer ()
- int getStatusCode () const
- const char * getStatusMessage () const
- int setPIDGains (int p, int i, int d)
- void doMainLoop (int updateDelay)

4.4.1 Detailed Description

Provides a server for motion mind controller.

A client (MMClient class) can connect to an object of this class to set desired velocities and positions through a shared memory interface. Use a separate program to set internal registers in the board.

Example Program: See example program for MMClient

4.4.2 Constructor & Destructor Documentation

4.4.2.1 MMServer::MMServer (const char * serverName, const char * port, int baud, int address, bool verbose = true)

Default constructor

Parameters:

serverName Name of the server

port The serial port name (example /dev/ttyS0, /dev/ser1)

baud The baud select and motor direction lines are common in connector J4. When the desired operating mode is 2 (button mode), the baud rate is selected based on motor direction. Otherwise, it is advised to set baud rate to 19.2 KBPS. Specify either 9600 or 19200 for the selected baud rate here.

address Multiple contollers may be daisy chained. Specify which device is being controlled by an instance of this object using this parameter. (address=1 if only one device present).

verbose Print device info if set to true.

4.4.2.2 MMServer::~MMServer ()

Destructor.

4.4.3 Member Function Documentation

4.4.3.1 void MMServer::doMainLoop (int updateDelay)

Main loop of the server.

Parameters:

updateDelay Delay (ms) between every update cycle.

4.4.3.2 int MMServer::getStatusCode () const

Returns:

0 if server status is OK, else -1.

4.4.3.3 const char* MMServer::getStatusMessage () const

Returns:

status message.

4.4.3.4 int MMServer::setPIDGains (int p, int i, int d)

Set the P, I and D gains

Returns:

0 on success, -1 on error.

The documentation for this class was generated from the following file:

 $\bullet \ \ MMClientServer.hpp$

4.5 MotionMind Class Reference

A driver for the Solutions Cubed Motion Mind DC motor controller Revision 4. #include <MotionMind.hpp>

Public Member Functions

```
MotionMind ()
~MotionMind ()
int init (const char *port, int baud, int address, bool verbose=true)
int changeSpeed (int16_t speed)
int moveToAbsolute (int32_t position)
int moveToRelative (int32_t position)
int moveAtVelocity (int16_t velocity)
int writeRegister (MMReg_t reg, int32_t val)
int writeStoreRegister (MMReg_t reg, int32_t val)
int32_t readRegister (MMReg_t reg)
int restore ()
int restore ()
```

4.5.1 Detailed Description

A driver for the Solutions Cubed Motion Mind DC motor controller Revision 4.

The documentation in this file supplements the technical manual for the motion mind controller which can be obtained from http://www.solutions-cubed.com/solutions%20cubed/MM1_-2005.htm. This driver is designed for the controller released with revision 4 of the above technical manual (late 2005). This driver class provides a RS232 communication interface to the controller, and is most useful for modes 3 (serial open-loop control) and 4 (serial PID position control) specified in the controller manual. The user must select the mode of operation by setting jumpers J5, and RS232 baud rate through J2.

Example Program:

```
// connect to the controller
ret = controller.init("/dev/ser1", 19200, 1);
if(ret == -1) {
fprintf(stderr, "Connection error\n");
return(-1);
// set gains p = 6000, I = 35, D = 200
if( controller.writeRegister(MMReg_pTerm, 6000) == -1 ) {
fprintf(stderr, "[main] ERROR setting P gain\n");
if( controller.writeRegister(MMReg_iTerm, 35) == -1 ) {
fprintf(stderr, "[main] ERROR setting I gain\n");
if( controller.writeRegister(MMReg_dTerm, 200) == -1 ) {
 fprintf(stderr, "[main] ERROR setting D gain\n");
// read current position
fprintf(stdout, "current position: %d\n", (unsigned int) controller.readRegister(MMReg_position));
// send desired position (in encoder counts x 4)
if( controller.moveToAbsolute(5000) == -1 ) {
 fprintf(stderr, "[main] ERROR sending desired position\n");
// wait
sleep(4);
// bye (controller automatically resets and stops motor on exit)
return 0;
```

4.5.2 Constructor & Destructor Documentation

4.5.2.1 MotionMind::MotionMind ()

The default constructor does nothing. Call init() to connect to the device.

4.5.2.2 MotionMind::~MotionMind ()

The default destructor. Frees resources.

4.5.3 Member Function Documentation

4.5.3.1 int MotionMind::changeSpeed (int16 t speed)

Modifies speed and direction of motor when controller is operated in mode 3 (serial open loop control). The device takes between 5 - 10 ms to respond to this command.

Parameters:

speed Value in the range -1023 to +1023. The direction is determined by the sign (- reverse, + forward) and the the absolute value sets the duty cycle of the input voltage (for example -512 => motor is driven in reverse with 50% duty cycle). The timer register (MMReg_timer) and the velocity limit register (MMReg_velocityLimit) determines the ramp up time required to achieve the new speed.

Returns:

0 on success, -1 on error.

4.5.3.2 int MotionMind::init (const char * port, int baud, int address, bool verbose = true)

Connects to the device through a specified serial port. Only RS232 binary data communication is supported. NOTE: This method must be called before calling any other method to interact with the hardware.

- Make sure jumper pins in J2 are set to 19.2 KBPS baud rate and Binary mode.
- Make sure that the PC's serial port is hooked to RS232 lines of the device.
- Ensure that mode of operation is selected through J5.

Parameters:

port The serial port name (example /dev/ttyS0, /dev/ser1)

baud The baud select and motor direction lines are common in connector J4. When the desired operating mode is 2 (button mode), the baud rate is selected based on motor direction. Otherwise, it is advised to set baud rate to 19.2 KBPS. Specify either 9600 or 19200 for the selected baud rate here.

address Multiple contollers may be daisy chained. Specify which device is being controlled by an instance of this object using this parameter. (address=1 if only one device present).

verbose Print device info if set to true.

Returns:

0 on success, -1 in case of error.

4.5.3.3 int MotionMind::moveAtVelocity (int16 t velocity)

Specify velocity when operating in mode 4 (serial closed loop). The PID filter must be tuned to get best results. The device takes between 5 - 10 ms to respond to this command.

Parameters:

velocity The desired velocity as a 2's compliment integer. The velocity measurement in the controller occurs over a 5 ms period. Hence, the desired velocity setting can be computed from the following equation: velocity = (MotorShaftRotations/Second * EncoderCount-PerRotation * GearRatio)/50. Use negative values for motion in reverse direction.

Returns:

0 on success, -1 on error.

4.5.3.4 int MotionMind::moveToAbsolute (int32 t position)

Specify an absolute motor position when operating in mode 4 (serial closed-loop). Ensure that the PID filter is tuned, and note that the encoder is decoded on a 4:1 ratio (i.e., if the encoder gives 500 pulses for 1 rotation of the shaft, send 2000 to rotate motor shaft by one full rotation. The device takes between 5 - 10 ms to respond to this command.

Parameters:

position Absolute position as a 32 bit 2's compliment number. Set velocity limit bit in the function register (MMFunc_velocityLimit) and load velocity limit register (mmcreg_-velocityLimit) to limit average velocity during motion.

Returns:

0 on success, -1 on error.

4.5.3.5 int MotionMind::moveToRelative (int32 t position)

Specify movement to a position relative to current position, when operating in mode 4 (serial closed loop). Ensure that the PID filter is tuned, and note that the encoder is decoded on a 4:1 ratio (i.e., if the encoder gives 500 pulses for 1 rotation of the shaft, send 2000 to rotate motor shaft by one full rotation. The device takes between 5 - 10 ms to respond to this command.

Parameters:

position Relative position as a 32 bit 2's compliment number. Set velocity limit bit in the function register (MMFunc_velocityLimit) and load velocity limit register (MMReg_-velocityLimit) to limit average velocity during motion.

Returns:

0 on success, -1 on error.

4.5.3.6 int32 t MotionMind::readRegister (MMReg t reg)

Read contents of a register. The returned values may have 1, 2 or 4 bytes of valid data, and may be in 2's compliment data format. See Section 6.0 (Register Definitions - Function/Status Bits) of the user manual for more information. The device takes between 5 - 10 ms to respond to this command. To check whether a particular bit (example MMFunc_posPwUp) is set in the function register, use this method as follows

```
int16_t func = readRegister(MMReg_function);
func &= MMFunc_posPwUp;
if(func) {
cout << "Position will be restored from EEPROM on power up" << endl;
}</pre>
```

The status register can be read in the same manner.

Parameters:

reg The register index.

Returns:

register value. The return value is undefined if the call didn't successfully execute.

4.5.3.7 int MotionMind::reset ()

Stops the motor and does a software reset. Allow a few seconds before calling any other method after a call to this function.

Returns:

0 on success, -1 on error.

4.5.3.8 int MotionMind::restore ()

Restore factory defaults. The motor is automatically stopped after successful execution of this command NOTE: The device takes up to 40 ms to respond to this command.

Returns:

0 on success, -1 on error.

4.5.3.9 int MotionMind::writeRegister (MMReg t reg, int32 t val)

This command can be used to set internal registers in any mode of operation. Register values set using this call are not retained after power cycling the controller. Use writeStoreRegister() to make permanent changes to register contents. The registers are 1, 2 or 4 bytes in length, and some of them expect 2's compliment data format. The user must take care to send properly formatted data to this call. The function and status registers (MMReg_function, MMReg_status) contain bit fields where each bit is related to a functionality. See Section 6.0 (Register Definitions - Function/Status Bits) of the user manual for more information. The device takes between 5 - 10 ms to respond to this command. To enable a particular bit (example MMFunc_posPwUp) in the function register, use this method as follows

```
int16_t func = readRegister(MMReg_function);
writeRegister(MMReg_function, func | MMFunc_posPwUp);
```

In order to disable a functionality, the user code would look like the following

```
int16_t func = readRegister(MMReg_function);
writeRegister(MMReg_function, func & ~MMFunc_posPwUp);
```

Parameters:

reg The register index. val the desired value.

Returns:

0 on success, -1 on error (including attempted write into a read-only register).

4.5.3.10 int MotionMind::writeStoreRegister (MMReg t reg, int32 t val)

This command can be used to set internal registers in any mode of operation. Register values set using this call are retained after power cycling the controller, and hence, used to modify default settings. Use writeRegister() to make temporary changes to register contents. The registers are 1, 2 or 4 bytes in length, and some of them expect 2's compliment data format. The user must take care to send properly formatted data to this call. The function register (MMReg_function) contains bit fields where each bit is related to a functionality. See Section 6.0 (Register Definitions - Function/Status Bits) of the user manual for more information. NOTE: The device takes up to 40 ms to respond to this command. Upon reception of a valid command, the motor is automatically stopped. The settings are made permanent by writing to the internal EEPROM which has a life time of about 1,000,000 write cycles. Avoid overuse of this function call.

Parameters:

```
reg The register index.val array with desired value (1,2, or 4 bytes).
```

Returns:

0 on success, -1 on error (including attempted write into a read-only register).

The documentation for this class was generated from the following file:

• MotionMind.hpp

| 22 | Motion Mind DC Motor Controller 1.0 Class Documentation |
|----|---|
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |
| | |

Motion Mind DC Motor Controller 1.0 File Documentation

5.1 MMClientServer.hpp File Reference

```
#include "MotionMind.hpp"
#include "putils/ShMem.hpp"
#include "putils/StatusReport.hpp"
#include <time.h>
#include <signal.h>
#include <semaphore.h>
```

Classes

- struct MMCommand
- class MMClient

A non-blocking client to MMServer.

• class MMServer

Provides a server for motion mind controller.

Defines

- #define MMCHANGESPEED 0x01
- #define MMMOVET OABS 0x02
- #define MMMOVET OREL 0x03
- #define MMMOVEATVEL 0x04

5.1.1 Define Documentation

- 5.1.1.1 #define MMCHANGESPEED 0x01
- $\mathbf{5.1.1.2} \quad \# \mathbf{define} \ \mathbf{MMMOVEATVEL} \ \mathbf{0x04}$
- 5.1.1.3 #define MMMOVETOABS 0x02
- $\mathbf{5.1.1.4} \quad \# \mathbf{define} \ \mathbf{MMMOVETOREL} \ \mathbf{0x03}$

5.2 MotionMind.hpp File Reference

```
#include <inttypes.h>
#include <stdlib.h>
```

Classes

- struct MMData
- class MotionMind

A driver for the Solutions Cubed Motion Mind DC motor controller Revision 4.

Typedefs

- ullet typedef enum MMReg MMReg_t
- typedef enum MMFunc MMFunc t
- typedef enum MMStatus MMStatus t
- typedef MMData MMData t

Enumerations

```
• enum MMReg {
 MMReg position = 0, MMReg velocityLimit, MMReg velocityFf, MMReg function,
 MMReg pTerm, MMReg iTerm, MMReg dTerm, MMReg address,
 MMReg pidScalar, MMReg timer, MMReg rcMax, MMReg rcMin,
 MMReg rcBand, MMReg rcCount, MMReg velocity, MMReg time,
 MMReg status, MMReg revision, MMReg mode, MMReg analogCon,
 MMReg analogFbck, MMReg pwmOut, MMReg indexPos }
• enum MMFunc {
 MMFunc posPwUp = 0x0001, MMFunc satProt = 0x0010, MMFunc savePos = 0x0020,
 MMFunc velLimit = 0x0040,
 MMFunc activeStop = 0x0080, MMFunc lastRc = 0x0100, MMFunc adStep = 0x0200,
 MMFunc adSerial = 0x0400,
 MMFunc enableDb = 0x0800, MMFunc selectFbck = 0x1000, MMFunc virtLimit =
 0x2000 }
• enum MMStatus {
 MMStatus negLimit = 0x1, MMStatus posLimit = 0x02, MMStatus brake = 0x04,
 MMStatus index = 0x08,
 MMStatus badRc = 0x10, MMStatus vnLimit = 0x20, MMStatus vpLimit = 0x40 }
```

```
Typedef Documentation
5.2.1
5.2.1.1
       typedef struct MMData MMData t
5.2.1.2
       typedef enum MMFunc MMFunc t
5.2.1.3
       typedef enum MMReg MMReg t
5.2.1.4
       typedef enum MMStatus MMStatus t
5.2.2
       Enumeration Type Documentation
5.2.2.1
       enum MMFunc
Enumerator:
    MMFunc\ posPwUp
    MMFunc\ satProt
    MMFunc savePos
    MMFunc\ velLimit
    MMFunc\ active Stop
    MMFunc lastRc
    MMFunc \ adStep
    MMFunc \ adSerial
    MMFunc\ enableDb
    MMFunc\ selectFbck
    MMFunc\ virtLimit
5.2.2.2
      enum MMReg
Enumerator:
    MMReg position
    MMReg \quad velocity Limit
    MMReg\ velocity Ff
    MMReg\ function
    MMReg\_pTerm
    MMReg\ iTerm
    MMReg dTerm
    MMReg \ address
    MMReg\ pidScalar
    MMReg\ timer
    MMReg rcMax
```

 $MMReg_rcMin$ $MMReg_rcBand$ $MMReg_rcCount$ $MMReg_velocity$

```
MMReg \ time
```

 $MMReg\ status$

 $MMReg_\,revision$

MMReg mode

 $MMReg \quad analogCon$

 $MMReg_analogFbck$

 $MMReg\ pwmOut$

 $MMReg\ indexPos$

5.2.2.3 enum MMStatus

Enumerator:

 $MMS tatus \ negLimit$

 $MMS tatus \ posLimit$

 $MMStatus \ brake$

 $MMStatus \ index$

 $MMStatus \ badRc$

 $MMS tatus \ \ vnLimit$

 $MMStatus \ vpLimit$

Index

| \sim MMClient | MMData, 13 |
|-------------------|---|
| MMClient, 9 | |
| \sim MMServer | ${ m MMCHANGESPEED}$ |
| MMServer, 14 | MMClientServer.hpp, 24 |
| \sim MotionMind | MMClient, 7 |
| MotionMind, 17 | \sim MMClient, 9 |
| | changeSpeed, 9 |
| address | getPosition, 9 |
| MMData, 13 | isServerStatusOk, 9 |
| analogCon | MMClient, 8 |
| MMData, 13 | moveAtVelocity, 9 |
| analogFbck | moveToAbsolute, 9 |
| MMData, 13 | moveToRelative, 10 |
| | MMClientServer.hpp, 23 |
| changeSpeed | MMClientServer.hpp |
| MMClient, 9 | MMCHANGESPEED, 24 |
| MotionMind, 17 | MMMOVEATVEL, 24 |
| command | MMMOVETOABS, 24 |
| MMCommand, 11 | MMMOVETOREL, 24 |
| | MMCommand, 11 |
| data | command, 11 |
| MMCommand, 11 | data, 11 |
| doMainLoop | guard, 11 |
| MMServer, 15 | position, 11 |
| dTerm | status, 11 |
| MMData, 13 | MMData, 12 |
| | address, 13 |
| function | analogCon, 13 |
| MMData, 13 | analogFbck, 13 |
| AD 111 | dTerm, 13 |
| getPosition | function, 13 |
| MMClient, 9 | indexPos, 13 |
| getStatusCode | iTerm, 13 |
| MMServer, 15 | mode, 13 |
| getStatusMessage | pidScalar, 13 |
| MMServer, 15 | - · · · · · · · · · · · · · · · · · · · |
| guard | position, 13 |
| MMCommand, 11 | pTerm, 13 |
| ' 1 D | pwmOut, 13 |
| indexPos | rcBand, 13 |
| MMData, 13 | rcCount, 13 |
| init | rcMax, 13 |
| MotionMind, 18 | rcMin, 13 |
| isServerStatusOk | revision, 13 |
| MMClient, 9 | status, 13 |
| iTerm | time, 13 |

| timer, 13 | MMReg mode |
|--------------------------------|-----------------------------------|
| velocity, 13 | MotionMind.hpp, 27 |
| velocityFf, 13 | $\mathrm{MMReg_pidScalar}$ |
| velocityLimit, 13 | MotionMind.hpp, 26 |
| $\mathrm{MMData_t}$ | ${ m MMReg_position}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| MMFunc | $\mathrm{MMReg_pTerm}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| MMFunc activeStop | ${ m MMReg_pwmOut}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 27 |
| $MMFunc_adSerial$ | ${ m MMReg_rcBand}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| $MMFunc_adStep$ | $\mathrm{MMReg_rcCount}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| $MMFunc_enableDb$ | $\mathrm{MMReg_rcMax}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| $MMFunc_lastRc$ | $\mathrm{MMReg_rcMin}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| ${\rm MMFunc_posPwUp}$ | ${ m MMReg_revision}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 27 |
| $MMFunc_satProt$ | ${ m MMReg_status}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 27 |
| $MMFunc_savePos$ | $\mathrm{MMReg_t}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| $MMFunc_selectFbck$ | ${ m MMReg_time}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| MMFunc_t | ${ m MMReg_timer}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| $MMFunc_velLimit$ | ${ m MMReg_velocity}$ |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| MMFunc_virtLimit | MMReg_velocityFf |
| MotionMind.hpp, 26 | MotionMind.hpp, 26 |
| MMMOVEATVEL | MMReg_velocityLimit |
| MMClientServer.hpp, 24 | MotionMind.hpp, 26 |
| MMMOVETOABS | MMServer, 14 |
| MMClientServer.hpp, 24 | ~MMServer, 14 |
| MMMOVETOREL | doMainLoop, 15 |
| MMClientServer.hpp, 24 | getStatusCode, 15 |
| MMReg | getStatusMessage, 15 |
| MotionMind.hpp, 26 | MMServer, 14 |
| MMReg_address | setPIDGains, 15 |
| MotionMind.hpp, 26 | MMStatus |
| MMReg_analogCon | MotionMind.hpp, 27 |
| MotionMind.hpp, 27 | MMStatus_badRc |
| MMReg_analogFbck | MotionMind.hpp, 27 |
| MotionMind.hpp, 27 | MMStatus_brake |
| MMReg_dTerm MotionMind.hpp, 26 | MotionMind.hpp, 27 MMStatus index |
| MMReg function | MotionMind.hpp, 27 |
| MotionMind.hpp, 26 | MMStatus negLimit |
| MMReg indexPos | MotionMind.hpp, 27 |
| MotionMind.hpp, 27 | MMStatus posLimit |
| MMReg iTerm | MotionMind.hpp, 27 |
| MotionMind.hpp, 26 | MMStatus t |
| mononmina.npp, 20 | 141141D 000 005 0 |

30 INDEX

| 25.4. 25.11. 22 | 100 |
|---|---|
| MotionMind.hpp, 26 | MMReg_velocity, 26 |
| MMStatus_vnLimit | MMReg_velocityFf, 26 |
| MotionMind.hpp, 27 | MMReg_velocityLimit, 26 |
| ${ m MMStatus_vpLimit}$ | $MMStatus_badRc, 27$ |
| MotionMind.hpp, 27 | MMStatus_brake, 27 |
| mode | $MMStatus_index, 27$ |
| MMData, 13 | ${ m MMStatus_negLimit,27}$ |
| MotionMind, 16 | $MMStatus_posLimit, 27$ |
| MotionMind, 17 | MMStatus vnLimit, 27 |
| MotionMind | MMStatus vpLimit, 27 |
| \sim MotionMind, 17 | $\overline{\text{MotionMind.hpp}}$ |
| changeSpeed, 17 | MMData t, 26 |
| init, 18 | $\overline{MMFunc}, 26$ |
| MotionMind, 17 | MMFunc_t, 26 |
| moveAt Velocity, 18 | $MMReg, \frac{2}{2}6$ |
| moveToAbsolute, 18 | MMReg t, 26 |
| moveToRelative, 19 | MMStatus, 27 |
| readRegister, 19 | MMStatus t, 26 |
| reset, 19 | moveAtVelocity |
| restore, 19 | MMClient, 9 |
| writeRegister, 20 | MotionMind, 18 |
| writeStoreRegister, 20 | $\begin{array}{c} \text{MotionWind, 18} \\ \text{moveToAbsolute} \end{array}$ |
| MotionMind.hpp, 25 | MMClient, 9 |
| MMFunc activeStop, 26 | MotionMind, 18 |
| MMFunc adSerial, 26 | moveToRelative |
| MMFunc adStep, 26 | |
| MMFunc enableDb, 26 | MMClient, 10 |
| MMFunc last Rc, 26 | MotionMind, 19 |
| | nidCoolon |
| MMFunc_posPwUp, 26 | pidScalar |
| MMFunc_satProt, 26 | MMData, 13 |
| MMFunc_savePos, 26 MMFunc_selectFbck, 26 | position |
| · | MMCommand, 11 |
| MMFunc_velLimit, 26 | MMData, 13 |
| MMFunc_virtLimit, 26 | pTerm |
| MMReg_address, 26 | MMData, 13 |
| MMReg_analogCon, 27 | pwmOut |
| MMReg_analogFbck, 27 | MMData, 13 |
| MMReg_dTerm, 26 | D 1 |
| MMReg_function, 26 | rcBand |
| MMReg_indexPos, 27 | MMData, 13 |
| MMReg_iTerm, 26 | rcCount |
| MMReg_mode, 27 | MMData, 13 |
| MMReg_pidScalar, 26 | rcMax |
| MMReg_position, 26 | MMData, 13 |
| MMReg_pTerm, 26 | rcMin |
| $MMReg_pwmOut, \frac{27}{}$ | MMData, 13 |
| MMReg_rcBand, 26 | $\operatorname{readRegister}$ |
| MMReg_rcCount, 26 | MotionMind, 19 |
| MMReg_rcMax, 26 | reset |
| MMReg_rcMin, 26 | MotionMind, 19 |
| MMReg_revision, 27 | restore |
| MMReg_status, 27 | MotionMind, 19 |
| MMReg_time, 26 | revision |
| MMReg_timer, 26 | MMData, 13 |
| | |

INDEX 31

```
\operatorname{setPIDGains}
        MMServer, 15
\operatorname{status}
        MMCommand, 11
        MMData, 13
_{\rm time}
        \operatorname{MMData},\, \color{red} 13
_{
m timer}
        \operatorname{MMData},\, \textcolor{red}{\mathbf{13}}
velocity
        MMData, 13
velocityFf
        MMData, 13
{\it velocityLimit}
        \operatorname{MMData},\, \textcolor{red}{\mathbf{13}}
{\bf write Register}
        {\rm MotionMind},\, {\color{red}20}
writeStoreRegister
        {\rm MotionMind},\, {\color{red}20}
```